

# Prep4King



- ✓ Online Tool, Convenient, easy to study.
- ✓ Instant Online Access
- ✓ Supports All Web Browsers
- ✓ Practice Online Anytime
- ✓ Test History and Performance Review
- ✓ Supports Windows / Mac / Android / iOS, etc.



- ✓ Installable Software Application
- ✓ Simulates Real Exam Environment
- ✓ Builds Exam Confidence
- ✓ Supports MS Operating System
- ✓ Two Modes For Practice
- ✓ Practice Offline Anytime



- ✓ Printable PDF Format
- ✓ Prepared by IT Experts
- ✓ Instant Access to Download
- ✓ Study Anywhere, Anytime
- ✓ 365 Days Free Updates
- ✓ Free PDF Demo Available



## Security & Privacy

We respect customer privacy. We use McAfee's security service to provide you with utmost security for your personal information & peace of mind.



## 365 Days Free Updates

Free update is available within 365 days after your purchase. After 365 days, you will get 50% discounts for updating.



## Money Back Guarantee

Full refund if you fail the corresponding exam in 90 days after purchasing. And Free get any another product.



## Instant Download

After Payment, our system will send you the products you purchase in mailbox in a minute after payment. If not received within 2 hours, please contact us.

<http://www.prep4king.com/>

aims to give you good guidance during the preparation for easy pass.

**Exam** : **700-070**

**Title** : Cisco TelePresence IX5000  
Series Immersive Solutions

**Vendor** : Cisco

**Version** : DEMO

NO.1 How many presentations can be shared in a direct IX5000-to-IX5000 call?

- A. two
- B. three
- C. four
- D. one

**Answer:** A

Explanation:

On an IX-to-IX point-to-point conference, you can share up to two presentation streams - for example, one presentation content source and one whiteboard source. If hosting a meeting locally with no videoconferencing, you can share up to three presentation streams.

Reference:

[http://www.cisco.com/c/en/us/td/docs/telepresence/ix\\_sw/8\\_x/admin/guide/ix\\_8\\_admin\\_guide/ix\\_sw\\_features.html](http://www.cisco.com/c/en/us/td/docs/telepresence/ix_sw/8_x/admin/guide/ix_8_admin_guide/ix_sw_features.html)

NO.2 How can you change presentation display options during a call?

- A. Open the share tray and drag the presentation to the desired location.
- B. Open the share tray and assign display numbers to each presentation.
- C. Open the system settings and reconfigure the display options.
- D. Open the participant list and drag the presentation to the desired location.

**Answer:** A

Explanation:

The share tray allows you to move and duplicate content to and from the main and presentation displays.

To show the share tray, tap Share.

To add content to the conference, drag the content from the share tray to the presentation area.

To remove content from the conference, drag the content from the presentation area to the share tray.

Reference: [http://www.cisco.com/c/dam/en/us/td/docs/telepresence/ix\\_sw/8\\_x/user/guide/ix-8-1ug.pdf](http://www.cisco.com/c/dam/en/us/td/docs/telepresence/ix_sw/8_x/user/guide/ix-8-1ug.pdf)

NO.3 Which step is required during pre-installation of the IX5000?

- A. Hang ceiling lights.
- B. Install wall panels.
- C. Verify that the room floor is level.
- D. Verify that appropriate licenses, upgrades, and tools are available.

**Answer:** D

NO.4 Where can you find packet-transmission statistics?

- A. Monitoring > Maintenance
- B. Monitoring > Network Data
- C. Monitoring > Statistics
- D. Monitoring > Call Info

**Answer:** B

**Explanation:**

Use the Network Data section to view packet transmission statistics collected from the network. Data is listed in columns labeled as if you were looking at the back of the system. For example, on an IX5000, the labels would indicate statistics from the left, center, and right codecs.

To monitor network statistics:

**Step 1**

In the Monitoring page, scroll down to Network Data. Your network data appears

Reference:

[http://www.cisco.com/c/en/us/td/docs/telepresence/ix\\_sw/8\\_x/admin/guide/ix\\_8\\_admin\\_guide/ix\\_sw\\_mntr.html](http://www.cisco.com/c/en/us/td/docs/telepresence/ix_sw/8_x/admin/guide/ix_8_admin_guide/ix_sw_mntr.html)

NO.5 What is the maximum image resolution of the 4K UHD camera display in the IX5000?

- A. 1080p60
- B. 1280p60
- C. 1080p30
- D. 720p30

**Answer: A**

**Explanation:**

Video resolution

Native support up to 1920 x 1080p, 60 fps

Content frame rate

Content sharing up to 1920 x 1080p resolution, 30fps

<http://www.cisco.com/c/en/us/products/collateral/collaboration-endpoints/ix5000-series/datasheetc78-733257.html>